AFATDS

SOFT WARE LOADING

Objectives

- Discuss when reloading software is required.
- Load AFATDS software
- Load Joint Master Unit List (JMUL)
- Load Service Pack 2

- Any time the information messages are ignored and the next step taken before OKing them, small errors are introduced to the database. This may not effect the processing right away but if the practice is continued the data base **will** become corrupt.
- You must wait for all informational messages before proceeding to the next step!
- For this reason before any operation or exercise begins you should reload software to remove any errors that may exist on the database.

Load Software

- Power on the system.
- While the system is powering on insert disk 1 of 3 into the CDROM.
- When the first window appears press **<Stop>** and **<A>** simultaneously.
- Type **boot cdrom** and **<Enter>**
- Type **afatds** for the system password

Load Software

- When disk 1 is done it will eject.
- Insert disk 2 and wait for the top light on the cd drive to stop blinking and press **<Enter>**
- When disk 2 is done it will eject.
- Insert disk 3 and wait for the top light on the cd drive to stop blinking and press **<Enter>**
- When disk 3 is done it will eject.
- New machine name (top) box is highlighted select **<Backspace>** to remove the word **cloner**.

Load Software

- New machine name (top) box is highlighted select **<Backspace>** to remove the word **cloner**. Enter **MCFSS#** (the number will come from the drive bay)
- Select **<Tab>** to highlight New Machine address (bottom) box and back space to remove the numbers **1.1.1.1** from the box and type **192.8.12.#** (the last digit will come from the drive bay door)
- If the last number is **01-09** it must be entered as a single digit **1-9**.
- **<OK>** and **<OK>** the reboot message.

Load the JMUL

- When the system log-in window is displayed, log-in as **sysadmin** password **afatds.**
- Insert the JMUL disk 1 of 1 in the CD drive.
- **Start> Programs>** and **X-term.**
- Move the cursor to the X-term window and type **COEInstaller**.
- The installer window will appear after a minute or two.

Load the JMUL

- On the installer window select **<Select Source> CDROM** and highlight the bottom line on the right side of the window (**AFAMULSegment.tar**) and **<OK>.**
- Select **<Read Contents>**
- **AFATDS Master Unit List** will appear in the bottom of the widow. Highlight it and select **<Install>** and **<OK>** the informational message.
- The Installer window will redisplay when complete. Select **<Exit>** and type **eject** in the X-term window to eject the CD.

Load the Service Pack

- On the installer window select **<Select Source> CDROM** and highlight the bottom line on the right side of the window **AFATDS_V632_SP2B.tar** and **<OK>.**
- Select **<Read Contents>**
- **AFATDS CORE Patch** will appear in the bottom of the widow. Highlight it and select **<Install>** and **<OK>** the informational message.
- The Installer window will redisplay when complete. Select **<Exit>** and type **eject** in the X-term window to eject the CD.

QUESTIONS?

Summary

- Explained when it is necessary to reload software.
- Loaded AFATDS software.
- Loaded the JMUL.
- Loaded the Service Pack.